

SET UP

Dio programa

osnovni nivo

Komandom *SET UP* mijenjamo vrijednosti parametara od kojih je zavisno djelovanje programa.

U komandni redak upišemo

Komandni redak

Komanda : <i>SET UP</i>

Nakon potvrde komande otvori se nova ekranska slika sa parametrima i njihovim vrijednostima. Po parametrima pomičemo se tipkama , ,  i . Vrijednosti parametara mijenjamo tako da se tipkom  ili  pomičemo po vrijednostima naprijed, a tipkom  unatrag. Kod numeričkih vrijednosti možemo vrijednost (broj) upisati.

Izlazak omogućava tipka .

U nastavku navedeni su pojedini parametri te njihove vrijednosti. Preporučene vrijednosti označene su zvjezdicom (*). Opisani su parametri koji utiču na događanje u segmentu COBISS/Pozajmica. Drugi parametri za taj program nisu značajni, ali preporučujemo da ih ne mijenjate jer su značajni za segment COBISS/Katalogizacija.

Keypad

Upotreba pomoćne tastature:

- application*: pomoćni dio tastature je u aplikacijskom načinu djelovanja (tipke pomoćnog dijela tastature djeluju kao komandne tipke),
- numeric: pomoćni dio tastature je u numeričkom načinu djelovanja.

Interpret

Interpretacija znakova na tastaturi:

- American: uglate zagrade, zagrade, tačku zarez, dvotačku itd. dobijemo bez tipke . Šumnike dobijemo tako da pritisnemo tipku , slovo "v" i osnovno slovo.
- COBISS*: šumnike dobijemo pritiskom na određene tipke (slovo "š" dobijemo tipkom za uglatu zagradu, "č" tipkom za tačku zarez itd.). Uglate zagrade, tačku zarez itd. dobijemo tako da najprije dvaput pritisnemo tipku  i zatim tipku za određeni znak.

Keyboard

Vrste tastature:

- QWERTY*: tastatura je postavljena na QWERTY način rada
- QWERTZ: tastatura je postavljena na QWERTZ način rada

Language

Jezik poruka:

- eng: jezik poruka je engleski
- scr: jezik poruka je srpski
- bos: jezik poruka je bosanski
- cro: jezik poruka je hrvatski
- mac: jezik poruka je makedonski
- slv: jezik poruka je slovenački.

Printer

Vrsta lokalnog štampača za ispise (za komande *PRT*, *PRTALL*, *ETI*, *PRTMEMB*):

- DL900, DL1100, DL4600 (eprom IZUM)
- DL5600 (eprom IZUM)
- DL2600 (eprom IZUM)
- DX2200 (eprom IZUM)
- DX2200 (download) (queue)
- DLxxxx (download) (queue)
- HP (COBISS Fonts)
- FUJITSU or EPSON 1
- FUJITSU or EPSON 2
- Unknown
- EPSON thermal line printer
- SLO Unknown
- FARGO (labels)
- DL1000, DL1150 (eprom COBISS)
- DL700, DL3800 (eprom COBISS)
- HP(PCL Fonts)
- Ther. line printer (CP 1250)
- Ther. line printer (CP 852)
- HP (COBISS Fonts) dupl. prt

- FUJITSU DL 3750 PLUS
- DATAMAX tiskalniki

Vrsta štampača se pohrani s obzirom na segment u koji smo trenutno prijavljeni, zato je moguće podešavanje različitih štampača u segmentima COBISS2/Katalogizacija, COBISS2/Pozajmica i COBISS2/Ispisi.

Queue

Broj sistemskog štampača za ispise (za komandu *SYSPRT*)

Cir search limit

Ograničavanje pretraživanja na lokalnom katalogu:

- none*: bez ograničenja pretraživanja
- noarticle: ograničavanje pretraživanja na zapise bez članaka

Cir print debt

Odredi, gdje će se ispisati potvrda prilikom podmirenja potraživanja odn. kod komande *PRTALL*:

- local*: na lokalnom štampaču, povezanom sa terminalom
- queue: na štampaču koji izaberemo između instaliranih štampača u biblioteci

Cir print eti

Odredi, gdje će se ispisati naljepnica sa podacima o članu, koju smo izradili komandom *ETI*:

- local*: na lokalnom štampaču, povezanom sa terminalom
- queue: na štampaču koji izaberemo između instaliranih štampača u biblioteci

Script

Niz znakova na štampaču:

- Cyr OFF Greek OFF OldCyr OFF*
- Cyr ON Greek OFF OldCyr OFF
- Cyr OFF Greek ON OldCyr OFF
- Cyr ON Greek ON OldCyr OFF
- Cyr OFF Greek OFF OldCyr ON
- Cyr ON Greek OFF OldCyr ON

- Cyr OFF Greek ON OldCyr ON
- Cyr ON Greek ON OldCyr ON

Za pripremu, štampanje i prijenos ispisa na nelatiničkim pismima potrebno je postaviti pojedinu vrstu pisma na *ON*:

- "*Cyr*" – *ćiriličko pismo*
- "*Greek*" – *grčko pismo*
- "*OldCyr*" – *staroćiriličko pismo*

Za pravilno štampanje in prijenos ispisa, postavljanja pisama moraju se podudarati s postavljanjima prilikom kreiranja pojedinih ispisa.

Broadcast

Primanje poruka telefonski (komanda *PHONE*), elektronskom poštom (komanda *MAIL*) ili obavijesti o izvršenom postupku (komanda *JOB*):

- PHONE MAIL JOB*
- NOPHONE MAIL JOB
- PHONE NOMAIL JOB
- NOPHONE NOMAIL JOB
- PHONE MAIL NOJOB
- NOPHONE MAIL NOJOB
- PHONE NOMAIL NOJOB
- NOPHONE NOMAIL NOJOB

Add FF to printout

- no*: na kraju ispisne liste sekvenca Form feed (FF) se ne doda
- yes: na kraju ispisne liste sekvenca Form feed (FF) se doda

COBISS2/Izposoja (Odd.01)	Nastavitev parametrov	DD.MM.LLLL
Keypad: application	Prefix: TI,AU,LA,PY,ID	
Interpret: COBISS	Format: BIB,SHOR,COPY,FULL,L10	
Keyboard: QWERTY	Expand code: yes	
Start level: 7	Hold format: new line	
Exit level: 1 low	Bold subfield: yes	
Language: slv	Key help: no	
Printer: 16 HP (PCL Fonts)	Non-stop help: no	
Queue: 18 (JETSET,Form=PRT_MAX)	Bold attr.: Enabled	
Condensed: no	Fast exit: no	
List divide: word	Hold level: 3 (2*SR,PR,AM,FI,RE)	
Def. card format: 10	Def. type: M	
Key repeat: yes	Script: Cyr OFF Greek OFF OldCyr OFF	
Cir search limit: none	Broadcast: PHONE MAIL JOB	
Cir print debt: local	Line mode: no	
Cir print eti: local	> Add FF to printout: yes	
Automatic display: no		
		TSTCIR::ZDENKA
Ukaz: SET UP		

SET UP - 1: Mij enjevanje vrijednosti parametara u SET UP-u